

# Microsoft Outlook 2019/Microsoft365 (Windows)

Prepare the following pieces of information in advance.

These wares displayed on screen when you subscribed. You will also find those on the Access Information Sheet that was sent to you.


In the following description which are shown in green, please replace it with your own details.

Name	Value
Mail password	
Mail address	xxx99999@xxx.att.ne.jp


I guide you about "Outlook2019" with this manual.

When you have you confirm existing setting, look from Step8.


Click "Outlook" on the Start Menu. Step1.




#### Step2. Please start Setup wizard.



① Start Microsoft Outlook and navigate to File at the top.




2 Click on the button Add Account under Account Information.




## Step3. Enter the following, and click "Connect".


When you change from Step3 to a screen of Step6, please omit Step4 from Step5.



#### Step4. Click "POP".





Step5. Enter the following on the "POP Account Settings" window. Click "Next".




Name	Value
Incoming mail	popssl.att.ne.jp
Port	995
This server requires encrypted connection (SSL/TLS)	Checked
Outgoing mail	smtpssl.att.ne.jp
Port	465
Encryption method	SSL/TLS


Step6. Enter Your mail password and Click Connect.






Step7. Please click "Done" after excluding a check of "Set up Outlook Mobile on my phone, too".






Step8. Please start "Management Profile".


① Start Microsoft Outlook and navigate to "File" at the top.




② Please click on "Account Settings", then "Manage Profiles".




#### Step9. Click "Email Accounts".



# Step10. You choose an account, and please click a "change".




## Step11. Please click "More Settings" if you finish input.




Name	Value	
Your Name	Your first and last name	
	e.g. SpinNet_Support	
Email Address	Your mail address	
	e.g. xxx99999@xxx.att.ne.jp	
Account Type	Select POP3.	
Incoming mail server	popssl.att.ne.jp	
Outgoing mail server (SMTP)	smtpssl.att.ne.jp	
User Name	Your mail address	
Password	Your mail password	

## Step12. ① Click the "General" tab and check it.


2 Click the "Outgoing Server" tab and check it.





Tab	Name	Value
General	Mail Account	e.g. SpinNet_Support
Outgoing Server	My outgoing server (SMTP) requires authentication	Checked
	User same settings as my incoming	
	mail server	


Step13. Click the "Advanced" tab and check it. and Click "OK".




Name	Value
Incoming Server	995
This server requires encrypted connection (SSL/TLS)	Checked
Outgoing Server	465
Use the following type of encrypted connection	SSL/TLS
Leave a copy of message on the server	Uncheckd
	* optional item

## Step14. Please operate as follows. This concludes the setting.


## ① Click "Next".




## 2 Click "Close".




# 3 Click "Finish".



Step15. Please click "Settings" after opening the tab of "Data Files", and choosing "Data File".




Step16. You set the suitable name and click "OK" later, and please close a window.




#### Step16. Please operate it as follows.

① Click "Close".



2 Click "Close".



This concludes the settings.